

# 使用 Outlook 2003 / 2007/ 2010

1. 新增帳戶 → 選擇《手動設定伺服器或其它伺服器類型》 → 點選下一步



新增帳戶

自動帳戶設定  
連線至其他伺服器類型。

電子郵件帳戶 (A)

您的名稱 (N):   
範例: 成凱倫

電子郵件地址 (E):   
範例: ellen@contoso.com

密碼 (P):   
重新鍵入密碼 (I):   
鍵入網際網路服務提供者給您的密碼。

簡訊 (SMS) (X)

手動設定伺服器設定或其他伺服器類型 (M)

< 上一步 (B)   下一步 (N) >   取消

2. 選擇《網際網路電子郵件》 → 點選下一步



新增帳戶

選擇服務

網際網路電子郵件 (I)  
連線至 POP 或 IMAP 伺服器，以傳送及接收電子郵件訊息。

Microsoft Exchange 或相容服務 (M)  
連線並存取電子郵件、行事曆、連絡人、傳真和語音信箱。

簡訊 (SMS) (X)  
連線至行動裝置訊息服務。

其他 (O)  
連線至下列顯示的伺服器類型。  
Microsoft Outlook Hotmail Connector

< 上一步 (B)   下一步 (N) >   取消

3. 輸入電子信箱各項的資訊  
POP3 : mail.silport-tech.com  
SMTP : mail.silport-tech.com
4. 點選《其他設定》

新增帳戶

網際網路郵件設定  
您的電子郵件帳戶需要這些設定才能生效。

**使用者資訊**  
您的名稱 (N): User  
電子郵件地址 (E): user@silport-tech.com

**伺服器資訊**  
帳戶類型 (A): POP3  
內送郵件伺服器 (I): mail.silport-tech.com  
外寄郵件伺服器 (SMTP) (O): mail.silport-tech.com

**登入資訊**  
使用者名稱 (U): user  
密碼 (P): \*\*\*\*\*  
 記住密碼 (R)  
 需要使用安全密碼驗證 (SPA) 登入 (Q)

**測試帳戶設定**  
在填入本視窗資訊後，建議您按下面的按鈕以測試您的帳戶。(網路必須連線)  
測試帳戶設定 (T)...

按 [下一步] 按鈕測試帳戶設定 (S)

**傳送新郵件到:**  
 新增 Outlook 資料檔 (W)  
 現有 Outlook 資料檔 (X)  
瀏覽 (B)

其他設定 (M)...

< 上一步 (B)   下一步 (N) >   取消

5. 選擇《外寄伺服器》的標籤，勾選《我的外寄伺服器需要驗證》，並選擇《使用與內送郵件伺服器相同的設定》。確認並完成操作。

網際網路郵件設定

一般   外寄伺服器   連線   進階

我的外寄伺服器 (SMTP) 需要驗證 (O)

使用與內送郵件伺服器相同的設定 (U)

使用下列登入 (L)

使用者名稱 (N):  
密碼 (P):  
 記住密碼 (R)


需要安全密碼驗證 (SPA) (Q)

在傳送郵件前登入內送郵件伺服器 (I)



確定   取消

## 使用 Outlook Express

1. 點選《工具》→《帳戶》後，將出現如下圖的視窗。點選《新增》→《郵件》



2. 依序輸入顯示名稱、電子郵件帳號



3. 輸入電子信箱各項的資訊


POP3 : mail.silport-tech.com

SMTP : mail.silport-tech.com



The screenshot shows a dialog box titled "網際網路連線精靈" (Internet Connection Wizard) with a close button in the top right corner. The main title is "電子郵件伺服器名稱" (Email Server Names). Below the title, there is a dropdown menu labeled "我的內送郵件伺服器是(S)" (My incoming mail server is) with "POP3" selected and a "伺服器" (Server) label. Underneath, there are two text input fields: "內收郵件 (POP3、IMAP 或 HTTP) 伺服器(I):" (Incoming mail server) containing "mail.silport-tech.com", and "外寄郵件伺服器 - SMTP(O):" (Outgoing mail server - SMTP) also containing "mail.silport-tech.com". At the bottom, there are three buttons: "< 上一步(B)" (Previous), "下一步(N) >" (Next), and "取消" (Cancel).

4. 輸入電子郵件的密碼




The screenshot shows the same dialog box, now at the "網際網路郵件登入" (Internet Mail Login) step. It prompts the user to "請建立網際網路服務提供者給您的帳戶名稱及密碼。" (Please create the account name and password provided by the Internet service provider). There are two text input fields: "帳戶名稱(A):" (Account name) containing "user", and "密碼(P):" (Password) containing "\*\*\*\*". Below the password field is a checked checkbox labeled "記憶密碼(W)" (Remember password). A note states: "如果您的網際網路服務提供者要求您使用 [安全密碼驗證] (SPA) 來存取您的郵件帳戶，請選擇 [使用安全密碼驗證登入] 選項。" (If your Internet service provider requires you to use [Secure Password Authentication] (SPA) to access your mail account, please select the [Use Secure Password Authentication Login] option). At the bottom, there is an unchecked checkbox labeled "使用安全密碼驗證 (SPA) 登入(S)" (Use Secure Password Authentication (SPA) login) and the same three navigation buttons as in the previous step: "< 上一步(B)", "下一步(N) >", and "取消".

5. 完成後，先如下圖所示，點選該帳號，再點選旁邊的《內容》按鈕



6. 選取《伺服器》標籤，找到底下的外寄郵件伺服器的地方，勾選《我的伺服器需要驗證》



7. 選取《使用與內送郵件伺服器相同的設定》。確認並完成操作。

